

DTRACK Plugin for Unity Game Engine 2019.x or later

This is a component for Unity 2019.1 or later with the purpose of native integration of the Advanced Realtime Tracking (ART) DTRACK (DTrack2 or DTRACK3) tracking solutions. This Unity Asset provides access to DTRACK tracking data, that is sent over network using UDP/IP datagrams. Each UDP packet contains one frame of tracking data including all outputs activated via the DTRACK software (see section **DTRACK Configuration**). This package currently supports the DTRACK Standard Body (6d), Flystick (6df2) and Fingertracking (gl) data formats.

Download

You can download a ready-to-use Unity package (UnityDTrackPlugin-vX.X.X.unitypackage) at [GitHub releases](#).

You can download or clone sources for this Asset package at [GitHub](#).

Prerequisites

To use this Asset the following components are required:

- Unity Editor 2019.1 or later
- Windows 64 bit, Linux 64 bit
- ART tracking system and DTrack2/DTRACK3
- UnityDTrackPlugin package (Asset)
- DTRACK3 User's Guide (*optional*)
- DTRACK3 Programmer's Guide (*optional*)

Creating the Unity DTRACK Plugin Package from Sources

If you downloaded a ready-to-use Unity package (UnityDTrackPlugin-vX.X.X.unitypackage), proceed with section **Importing Unity Package**.

In order to create a Unity package from the provided sources, follow the steps below.

1. Download or clone sources for this Asset package (see section **Download**)
2. Launch Unity Hub
3. Create new Unity project (e.g., "MyUnityProject")
4. Extract the asset package, if applicable
5. Copy the content of directory *UnityDTrackPlugin* to your projects asset directory (`/path/to/unity/projects/MyUnityProject/Assets/DTrack`)
6. Export package (right-click on **DTrack** in the **Project** window and select *Export Package...*)

Please note: if you created the Unity package from sources and you want to try the available example scene, you need to assign DTrack scripts and to configure the plugin manually (see section **Plugin Configuration**).

Importing Unity Package

1. Launch Unity Hub
2. Create/Open Unity project
3. Import package (*Assets* → *Import Package...* → *Custom Package...*)

Updating from Unity DTRACK Plugin v1.0.3

To update the DTRACK Plugin within an existing Unity project it's necessary to replace the entire directory `/path/to/unity/projects/MyUnityProject/Assets/DTrack/` .

1. Launch Unity Hub
2. Open Unity project
3. Remove directory `/path/to/unity/projects/MyUnityProject/Assets/DTrack/` , either manually or in Unity Editor (*Project* → *Assets* → *DTrack* → (right click) *Delete*)
4. Install the DTRACK Plugin from Unity package (see above)

There's no need to adjust settings in already attached scripts (**DTrack**, **DTrackReceiver6Dof**, **DTrackReceiverFlystick**).

Please note: the so far used 'Unity events' to notify pressed Flystick buttons were declared deprecated and will be replaced in some future version of the plugin. Please don't use them in new projects (see section **Applying Flystick Data**).

Tip: if after an update existing button event settings (*Button Press Event X*, now denoted as *Button X Pressed Event Deprecated*) are not shown in Unity Editor, exiting and re-starting of the Unity Editor might help.

DTRACK Configuration

Find here a quick-start guide to DTRACK. For details, please refer to your DTRACK3 User's Guide and DTRACK3 Programmer's Guide, that is shipped with the DTRACK distribution. In this section we assume that the ART tracking system is properly set up and a room calibration was done. Further, a set of Standard Bodies and/or Flysticks and/or Fingertracking hands is calibrated.

Room Calibration


For general information about the DTRACK room calibration and room adjustment see the DTRACK User's Guide. Here we discuss details relevant for use with the Unity Engine.

The calibration angle tool which comes with your ART tracking system defines the coordinate system layout in your tracking area. It consists of four retroreflective or active markers mounted onto an L-shaped frame.



The marker on top of the edge of this L-shape by default designates the origin of the DTRACK coordinate system. When using the *Normal* calibration mode (see figure below), the long arm of this L-shape corresponds to the X axis and the short arm to the Y axis. DTRACK coordinates refer to a right-handed coordinate system, so when the tool is placed flat on the ground with the markers pointing up the Z axis points upwards.

wand length [mm]
410,00



marker distances Room Calibration Set 410 (high) ▼
A (1-2) [mm] 384,0
B (1-4) [mm] 114,0
C (1-3) [mm] 225,0
height [mm] 43,0



coordinate system
Normal ▼

☐ re-calibration (without angle tool)

Show details Transfer Calibrate Exit

The plugin transforms a right-handed position of a DTRACK 6DOF measurement to a left-handed Unity position by switching the Y and Z axes, i.e.,

$$(X_{\text{Unity}}, Y_{\text{Unity}}, Z_{\text{Unity}}) = (X_{\text{DTRACK}}, Z_{\text{DTRACK}}, Y_{\text{DTRACK}}).$$



DTRACK offers a multitude of ways to adjust coordinate systems for room and bodies, e.g., offsets, scaling, additional rotations, or shifting the origin of bodies. Consult your manual for details on *Room adjustment* and *Body adjustment*.

Setting Outputs

To configure the tracking data stream generated by DTRACK, execute these steps:

1. Open dialog *Output Settings* via menu *Tracking* → *Output* (DTRACK3) or *Settings* → *Output* (DTrack2), respectively
2. Activate a channel if needed
3. Fill in hostname or IP address, and UDP port number of the device receiving tracking data
4. Select outputs you are interested in (i.e., currently frame counter fr , 6DOF Standard Body $6d$, Flystick $6df2$ and Fingertracking gl are supported)

Channel 1
Channel 2
+

☒ active

send to
UDP port

my.un^unity.hostname.or.ip
5000

☐ this computer
send data divisor

☐ multicast (224.0.1.0 - 239.255.255.255)
1

Identifier	Description
<input checked="" type="checkbox"/> fr	frame counter
<input type="checkbox"/> ts	timestamp
<input type="checkbox"/> st	system status
<input type="checkbox"/> 6dcal	number of calibrated bodies
<input checked="" type="checkbox"/> 6d	6DOF standard body
<input type="checkbox"/> 6di	6DOF inertial body
<input type="checkbox"/> 3d	3DOF marker
<input checked="" type="checkbox"/> 6df2	Flystick
<input type="checkbox"/> 6dmt2	Measurement Tool
<input type="checkbox"/> 6dmtr	Measurement Tool reference
<input type="checkbox"/> glcal	number of calibrated Fingertracking hands
<input checked="" type="checkbox"/> gl	Fingertracking hand


☐ act as router for tracking output

Exit


Identifying Body IDs

There are several ways to identify the ID numbers of DTRACK Standard Bodies, Flysticks and Fingertracking hands, as needed later to configure the Unity plugin. E.g. refer to column *ID* in dialog *Body Administration* via menu *Tracking* → *Body*

Administration (DTRACK3) or Settings→ Body Administration (DTrack2).




Note that listed Flystick IDs are prefixed with a capital F, as well as listed Fingertracking hand IDs are prefixed with a capital H. When referencing Flysticks or Fingertracking hands from within Unity, this prefix must be removed.




Plugin Configuration

Streaming position, rotation and button events data from DTRACK tracking systems to objects in your scene, requires appropriate network settings. In your scene add an *Empty* game object and give it a name, e.g., **DTrackSource**. To this object attach the **DTrack** script via *Add Component*→ *Scripts*→ *DTrack*→ *DTrack*. Set *Listen Port* number matching the setting for DTRACK (see section **Setting Outputs**). Note that position data in the DTRACK output stream have unit millimeters. The DTRACK Unity Plugin converts such values to unit meter.



Applying 6DOF Standard Body Data


In your scene attach via *Add Component* the DTrack script **DTrackReceiver6Dof** to an object you want to receive positional and rotational data. In the `DTrackReceiver6Dof` mask type in the ID that was assigned to the Standard Body by DTRACK (see section **Identifying Body IDs**).



When the ART tracking system is running, you should now be able to see *Position* and *Rotation* data in the **Transform** box, as soon as you switch to *Play* mode.


Applying 6DOF Standard Body Data to the Camera

For non-static, point-of-view cameras, you can attach a DTRACK Receiver with positional and rotational data, e.g. of a 6DOF Standard Body.



Applying Flystick Data


In your scene attach via *Add Component* the DTrack script **DTrackReceiverFlystick** to an object you want to receive positional and rotational data. In the `DTrackReceiverFlystick` mask type in the ID that was assigned to the Flystick by DTRACK (see section **Identifying Body IDs**, without prefixed capital F).



DTrack script **DTrackReceiverFlystick** can send 'Unity events' to announce changed Flystick buttons or joystick values to scripts attached to arbitrary game objects. It provides:

- 8 events on changed Flystick buttons corresponding to the (maximum) number of 8 buttons of Flystick2+ (*Button X Changed Event*); an event is invoked once every time a button is pressed or released
- One event on changed Flystick joystick values (horizontal and vertical) (*Joystick Changed Event*); the event is invoked every time one of the values has changed
- One event on changed trigger value (just available at Flystick2+) (*Analog 3 Changed Event*); the event is invoked every time the value has changed

Please note: the so far (Unity DTRACK plugins v1.0.X) used 'Unity events' to notify pressed Flystick buttons (*Button Press Event X*) were declared deprecated and will be replaced in some future version of the plugin. Please don't use them in new projects.




See script **ExampleFlystickListener** on how to receive these 'Unity events' in your scripts. To register an own listener routine first create an additional entry in the wanted *Event* element by pressing **+**. Then drag and drop the game object, that should receive the event, from the *Hierarchy* tree into the *Event* element. Finally choose the listener routine's name.

Applying Fingertracking Data

The DTRACK Plugin provides support of ART Fingertracking, so far adjusted for usage with 'Leap Motion Realistic Male Hands' (by Storkplay, available at the Unity Asset Store), or hand models with equivalent rig and coordinate systems:

- <https://assetstore.unity.com/packages/3d/characters/humanoids/leap-motion-realistic-male-hands-109961>




Add one of the *Prefabs* of your **LMRealisticMaleHands** asset to your scene.

Within the root object of the created left or right hand (Hand_0X_L or Hand_0X_R) now two components with missing scripts appear. Remove these components via *Remove Component*, attach instead via *Add Component* the DTrack script **LMRealisticHandMapper**. It automatically will attach also a DTrack script **DTrackReceiverHand**.

In **DTrackReceiverHand** mask enter the *Hand Id* that was assigned to the Fingertracking device by DTRACK (see section **Identifying Body IDs**, without prefixed capital H).

In **LMRealisticHandMapper** mask first ensure that the number of elements in list *Fingers* is 5. Now enter links to the corresponding game objects of the hand, for *Wrist* (L_Wrist or R_Wrist) and the fingers' root joints (L_Finger_Index_A, ... OR R_Finger_Index_A, ...). This can be done e.g. by dragging and dropping the objects from the *Hierarchy* tree into the **LMRealisticHandMapper** mask. The elements of *Fingers* have to be ordered as: thumb, index, middle, ring, pinky.



If the real size of the person's hand is differing too much from the hand model's size, it might be useful to modify the *Scale* factor in the **Transform** box of the hand's root object (Hand_0X_L or Hand_0X_R). If setting *Automatic Scale* is enabled, the hand mapper script tries to find a suitable value automatically.

Advanced Realtime Tracking GmbH & Co. KG
Am Oeferl 6
82362 Weilheim i. OB
Germany

<http://ar-tracking.com>